

**NAME**

devlink-dpipe – devlink dataplane pipeline visualization

**SYNOPSIS**

**devlink** [ *OPTIONS* ] **dpipe** { **table** | **header** } { *COMMAND* | **help** }

*OPTIONS* := { -V[ersion] }

**devlink dpipe table show** *DEV* [ **name** *TABLE\_NAME* ]

**devlink dpipe table set** *DEV* **name** *TABLE\_NAME*

**devlink dpipe table dump** *DEV* **name** *TABLE\_NAME*

**devlink dpipe header show** *DEV*

**devlink dpipe help**

**DESCRIPTION**

**devlink dpipe table show - display devlink dpipe table attributes**

**name** *TABLE\_NAME*

Specifies the table to operate on.

**devlink dpipe table set - set devlink dpipe table attributes**

**name** *TABLE\_NAME*

Specifies the table to operate on.

**devlink dpipe table dump - dump devlink dpipe table entries**

**name** *TABLE\_NAME*

Specifies the table to operate on.

**devlink dpipe header show - display devlink dpipe header attributes**

**name** *TABLE\_NAME*

Specifies the table to operate on.

**EXAMPLES**

**devlink dpipe table show** pci/0000:01:00.0

Shows all dpipe tables on specified devlink device.

**devlink dpipe table show** pci/0000:01:00.0 **name** mlxsw\_erif

Shows mlxsw\_erif dpipe table on specified devlink device.

**devlink dpipe table set** pci/0000:01:00.0 **name** mlxsw\_erif **counters\_enabled** true

Turns on the counters on mlxsw\_erif table.

**devlink dpipe table dump** pci/0000:01:00.0 **name** mlxsw\_erif

Dumps content of mlxsw\_erif table.

**devlink dpipe header show** pci/0000:01:00.0

Shows all dpipe headers on specified devlink device.

**SEE ALSO**

**devlink(8)**, **devlink-dev(8)**, **devlink-monitor(8)**,

**AUTHOR**

Jiri Pirko <jiri@mellanox.com>